

glassesArrangement (GlassesArrangement)

b2boptic → items → item → pair → lens → rxDataFn → near → glassesArrangement



slot	
type	integer
unity	none
occurs	1
description	the cell number of the lens in a trial frame. From the frame plane the cells are counted towards the eye with -1 and descending. In the other direction the cells are counted from the frame plane with 1 and ascending.
sphere	
type	float
unity	degree
occurs	1 or if cylinder or prism is present then 0
description	
revers (attribute of sphere)	
type	bool
use	optional
default	false
description	true if the label is towards the eye
cylinder	
type	Cylinder
occurs	1 or if sphere or prism is present then 0
description	
revers (attribute of cylinder)	
type	bool
use	optional
default	false
description	true if the label is towards the eye
prism	
type	Prism
occurs	1 or if sphere or cylinder is present then 0
description	
revers (attribute of prism)	
type	bool
use	optional
default	false
description	true if the label is towards the eye

```
<xs:complexType name="GlassesArrangement">
  <xs:sequence>
    <xs:element name="slot" type="xs:integer"/>
    <xs:choice>
```

```
<xs:element name="sphere">
  <xs:complexType>
    <xs:simpleContent>
      <xs:extension base="xs:float">
        <xs:attribute name="revers" type="xs:boolean"
default="false"/>
      </xs:extension>
    </xs:simpleContent>
  </xs:complexType>
</xs:element>
<xs:element name="cylinder">
  <xs:complexType>
    <xs:complexContent>
      <xs:extension base="Cylinder">
        <xs:attribute name="revers" type="xs:boolean"
default="false"/>
      </xs:extension>
    </xs:complexContent>
  </xs:complexType>
</xs:element>
<xs:element name="prism">
  <xs:complexType>
    <xs:complexContent>
      <xs:extension base="Prism">
        <xs:attribute name="prismSlope" type="PrismSlope"
use="required"/>
      </xs:extension>
    </xs:complexContent>
  </xs:complexType>
</xs:element>
</xs:choice>
</xs:sequence>
</xs:complexType>
```

From:
<https://wiki2.b2boptic.com/> - **wiki2.b2bOptic.com**

Permanent link:
<https://wiki2.b2boptic.com/en:lensorder:version010606:complextypes:glassesarrangement:near>

Last update: **2025/04/14 10:23**

